

# [Contents]

Safety Precautions  
Revisions  
Introduction  
Parts of This Manual  
How to Use This Manual  
Abbreviations



## **Getting started**

### **1 Getting started**

---

1.1 What GPPW can do .....	1- 1
1.2 Easy installation of GPPW .....	1- 5
1.3 Required items to gain access to PLC .....	1- 9
1.4 Operation flow .....	1-11



## **Basics**

### **1 Introduction**

---

1.1 How to use the mouse .....	2- 1
1.2 Common mouse operations .....	2- 3
1.3 Screen configuration .....	2- 7

### **2 Basics for GPPW operations**

---

2.1 What is a "project"? .....	2- 9
2.2 Starting GPPW .....	2-11
2.3 Ending a GPPW session .....	2-13
2.4 Designation of project .....	2-15
2.5 Frequent operations .....	2-19

**3**  
**Offline  
operations**

**1** **Creating a circuit**

---

- 1.1 Creating a new project ..... 3- 1
- 1.2 Creating a circuit with list expressions (mnemonic language) .. 3- 3
- 1.3 Creating a circuit with tool buttons ..... 3- 7
- 1.4 Converting a created program ..... 3-11
- 1.5 Creating a circuit with list commands..... 3-13
- 1.6 Saving a created project ..... 3-15
- 1.7 Reading a saved project ..... 3-17

**2** **Editing a circuit**

---

- 2.1 Correcting part of a circuit ..... 3-19
- 2.2 Cutting and copying a circuit block ..... 3-21
- 2.3 Inserting or deleting a line ..... 3-25
- 2.4 Creating and deleting a ruled line ..... 3-27

**3** **Searching a circuit**

---

- 3.1 Searching with a designated device ..... 3-29
- 3.2 Searching with a step No. .... 3-31

**4** **Replacing within a circuit**

---

- 4.1 Replacing with a designated device ..... 3-33
- 4.2 Replacing open contact with close contact and vice versa ..... 3-37

**5** **Explaining circuit components**

---

- 5.1 Creating device comments ..... 3-41
- 5.2 Creating statements for each circuit block ..... 3-45
- 5.3 Creating a note for coil and application instruction ..... 3-47

**6** **Editing comments**

---

- 6.1 Correcting device comments ..... 3-49
- 6.2 Deleting (cutting) device comments ..... 3-51
- 6.3 Copying device comments ..... 3-55
- 6.4 Searching statements and notes ..... 3-57
- 6.5 Correcting statements and notes ..... 3-59

**3**  
**Offline  
operations**

**4**  
**Online  
operations**

**5**  
**Useful  
functions**

**7** **Printing**

---

7.1 Printing a circuit ..... 3-61

7.2 Printing contacts or coils in use ..... 3-63

7.3 Printing the device in use ..... 3-65

7.4 Printing a list of device comments in use ..... 3-67

**1** **Writing and reading to/from the PLC CPU**

---

1.1 Writing data to the PLC CPU ..... 4- 1

**2** **Monitoring PLC status**

---

2.1 Monitoring circuit status ..... 4- 4

2.2 Monitoring designated devices ..... 4- 6

**3** **Debugging a created circuit**

---

3.1 Turning ON/OFF contact positively ..... 4- 8

3.2 Executing a program step by step ..... 4-10

**4** **Online change**

---

4.1 Writing data during a run of the PLC CPU ..... 4-12

4.2 Changing data during monitoring, and writing during a run .... 4-14

**1** **Offline operations**

---

1.1 Associating multiple programs ..... 5- 1

1.2 Changing function keys in GPPA, GPPQ, and MEDOC formats · 5- 5

1.3 Setting the designated projects for quick start-up ..... 5- 7

1.4 Converting files from GPPA format to GPPW format ..... 5- 9

1.5 Changing project PLC type ..... 5-17

**2** **Operations with Windows functions**

---

2.1 Using Excel files as device comment ..... 5-19

2.2 Using Word files as device comment ..... 5-21

2.3 Opening and editing multiple projects ..... 5-23



## ***Useful functions***

## ***Appendix***

### **3** **Using Logic Test functions**

---

- 3.1 Learning operation procedures ..... 5-27
- 3.2 Creating emulation of I/O and special unit ..... 5-29
- 3.3 Monitoring device status ..... 5-33

### **Appendix**

---


- App.1 Short cut key list ..... A- 1
- App.2 Circuit creation list ..... A- 7

Index


# 5 Useful functions

## 1.4 Converting files from GPPA format to GPPW format

This section explains converting files from GPPA format to GPPW format.



1) Click the [Project]-[Import file]-[Import from GPPA format file] menu.




2) Click **Browse**. (Use **Browse** to check the drive/path name, system name and machine name. If these information are known, input them directly.)




**To the following page //**

**From previous page**



- 3) Select drive/path name, system name, and machine name. After selection, click **OK**





- 4) Select if all (**Select all**) or part of GPPA data is converted to GPPW.

- 5) After selection, click **Execute** to execute conversion. When message **Completed** appears, conversion is completed.

# 5 Useful functions

## Notes for converting GPPA comment files to GPPW comment files

If comments in comment1 and comment2 and extension comments are attached to the existing data, the comment data are converted to GPPW common comments. If the comments in comment1 and comment2 and extension comments overlap, extension comment 1 takes priority and is converted first.





```

COMMON DEVICE
-----
X.Y - SP.M - SE.D
-----
MAIN PROGRAM          SUB PROGRAM
-----
M - C -
L - D -
S - E -
E - F -
F - E -
T - I -
  
```

—Notes for converting GPPQ comment files to GPPW files—

Program comments created by GPPQ are converted as they are.

Since GPPQ does not have a concept of common comment as GPPW does, common comments of GPPQ can be converted to common comment of GPPW by changing the file name to "COMMENT".





# 5 Useful functions

## Notes for writing GPPW data to ACPU/GPPA format files

Before writing data created by GPPW to ACPU, or to a floppy disk as a GPPA file, specify the memory capacity of the PC parameter (comment and extension comment) and the comment range for writing.

Operations for setting the device comment are explained by using the following circuit.



2) Select and click




To the following page //

- 1) Display the device comment edit screen.


Part 3, 5.1.

- 2) Select [Edit]-[Setup comment change].

**From previous page**



- 3) Select comment type [Comment2] by using the [Program common] tab.
- 4) Set X, Y device range from "0" to "7F".
- 5) Select "T" for the extension comment, and set the range from "0" to "10".
- 6) After setting, click [OK].



- 7) By selecting the [Each program] tab, other ranges such as M, L, and S can be set for the main program and sub-programs. Since "X and Y" in the example circuit here are allocated to the common device, and "T" to extension comment 1, the devices are not set in each program screen. Now, setting of comment range is completed.


Go to setting operation of comment memory capacity.




**To the following page**

## 5 Useful functions

*From previous page*




- 8) Double click [PLC parameter] and open the [parameter] dialog box.



- 9) Set the comment memory capacity to "4" and extension comment memory capacity to "2".

After setting, click **End setup**.



 **Hint!**  
By converting files created by GPPW to GPPA format and saving them in floppy disks, the files can be used if the user has GPPA.


# 5 Useful functions

## 1.5 Changing project PLC type


This section explains changing project PLC type set in project creation.

Here, operations for changing PLC type "A3A" to "Q3A" are described.


(Changing PLC type from A series to QnA series and vice versa involves restrictions. For detail, refer to the GPPW operating manual.)



- 1) Click the [Project]-[Change PLC type] menu.




- 2) Click the [PLC series] list button, and select PLC series to change. Here, select "QnACPU".




- 3) Click the [PLC type] list button, and select PLC type to change. Here, select "Q3A".
- 4) Click the [OK] button.

**To the following page //**

**From previous page**



5) A dialog box to confirm change is displayed. Click the **Yes** button.



6) Confirm that the PLC type on the status bar at the bottom of the screen is changed to "Q3A".

# 5 Useful functions

## 2 Operations with Windows functions


Windows is a well-known OS that is used worldwide. This section explains using Windows functions.

### 2.1 Using Excel files as device comment


This section explains using Excel files to create device comments.

The following explanation assumes that Excel and GPPW are running.


#### (Operations in Excel)



- 1) Click the cell containing the comment created.
- 2) Drag the mouse to designate the range to be used as comments. The designated area is highlighted.



- 3) Click  on the tool bar of Excel. The comments in the designated range are copied.




**To the following page //**

**From previous page**




**(Operations on GPPW)**





4) Click the position to paste the comment and move the cursor.

**Point**  
 Set the cursor position at the top of the paste range.  
 When pasted, the data is overwritten.



5) Click  on the tool bar.



6) Now the comments are created.


**Hint!**  
 For comment...  
 Part 3, 5.1 

# 5 Useful functions

## 2.2 Using Word files as device comment

This section explains using documents created by Word as device comments.  
The following explanation assumes that Word and GPPW are running.


### (Operations on Word)




- 1) Input comments in Word.  
Press the **Enter** key and feed line after each device comment.

### Point


If comments are input without line feed, the data is considered as one device comment.  
Be sure to feed line for each device comment.



- 2) Click the top of the comment created.
- 3) Drag the mouse to designate the range to be used as comments. The designated area is highlighted.



- 4) Click  on the tool bar of Word.  
The comments in the designated range are copied.






**To the following page //**

**From previous page**



**(Operations on GPPW)**



5) Click the position to paste the comment and move the cursor.


**Point**  
Set the cursor position at the top of the paste range.

6) Click  on the tool bar.

**Short cut key**  
Ctrl + V

7) Now the comments are created.

**Hint!**  
If a line feed is input between comments, a comment column is blanked.



For comment...  
Part 3, 5.1


### 2.3 Opening and editing multiple projects

Since the GPPW can edit only one project at a time, multiple GPPWs must be run to edit multiple projects simultaneously. Running multiple GPPWs allows cutting, copying, and pasting operations for programs and comments among different projects.


This section explains inserting a circuit block copied in Project 1 to Project 2.

The following explanation assumes that Projects 1 and 2 are already running.


#### (Operations for Project 1)



- 1) Move the cursor to step No. of the circuit block in Project 1 which is to be copied.



- 2) Drag the mouse vertically to designate the range to be cut or copied. The designated area is highlighted.




- 3) Click  on the tool bar. The highlighted area is released, and the circuit of the designated range is copied.

#### Hint!


To designate a single-line circuit block, drag horizontally for easier range designation.



**To the following page //**



**From previous page**




- 4) Move the cursor to the screen of Project 2, and click.

**Hint!**


Projects can be switched by using the task bar.





**(Operations for Project 2)**



- 5) Click the circuit block (any position) under the insert position, and move the cursor.



- 6) Click  on the tool bar.



- 7) The copied circuit block is inserted to the Project 2 circuit.

**Hint!**

Editing operations for circuits and comments between projects are same as editing within a project.

For methods of editing circuits...

 Part 3, Chapter 2. 

For methods of editing comments...

 Part 3, Chapter 6. 

### 3 Using Logic Test functions

The Logic Test function (option) is a tool that enables debugging the sequence programs created by users without connecting PLC CPU.

This function allows debugging by using a personal computer without a debugging equipment such as PLC CPU.

This section explains the operations of the Logic Test function.

#### —Outline of Logic Test function (LLT)—

Installing the Logic Test function (LLT) additionally to the personal computer installed with GPPW enables debugging of the sequence programs in off-line status (when GPPW is not connected to external devices such as PLC).

It also allows quick development of sequence programs because program creation and debugging can be performed on the same personal computer.

Debugging by the Logic Test function (LLT) is performed by writing sequence programs created with GPPW to the LLT. Writing is executed automatically with start-up of the Logic Test function.

#### —Functions supported by Logic Test function (LLT)—

- ◆ When the Logic Test function (LLT) is installed, the online menu of GPPW becomes available in the same way as it is connected to PLC CPU. (PLC CPU emulation)

Online menu	Description
Circuit monitor, device monitor	Monitors operating status.
Device test	Overwrites the device value positively during monitoring.
PLC writing	Writes parameter files and program files.
Step execution	Operates the sequence program step by step.
Partial operation	Executes the designated steps or pointer range of the program.
Remote operation	Operates the status of the Logic Test function (LLT).


◆ Functions performed by Logic Test function (LLT)

Function	Description	Refer to
Monitor test	Monitors the condition of device memory, and tests the positive ON/OFF of devices and the change of present values.	3.3
I/O system setting	Simulates machine operations by simple setting.	3.2

Note: Other than the above functions, the Logic Test function supports the "Tool function" which allows temporal storage of LLT device data and buffer memory data of special function unit.

——Note for start-up of Logic Test function (LLT)——

- ◆ If QnACPU is selected for PLC series, set the [Program] tab of the PLC parameter for GPPW as follows. (For A series, no setting is required.)




——Processing time of sequence program in Logic Test function——

The actual processing time of the sequence program depends on the performance of the personal computer and the operation environment of other applications.


## 3.1 Learning operation procedures

This section explains debugging with the Logic Test function (LLT).

The following explanation assumes that GPPW and the Logic Test function are installed.



- 1) Confirm that the project is open, and click the [Tools]-[Start ladder logic test] menu.



- 2) The Logic Test function starts-up.


 **Hint!**

- When the Logic Test function (LLT) starts-up, the parameter and program are written simultaneously (equivalent to PLC write).
- If QnACPU is used, program setting of the PLC parameter is required.




**To the following page //**



From previous page //




- 3) Click on the GPPW screen to activate the screen.



- 4) Click the  button and set the screen to the monitor mode.



- 5) Circuit monitoring is executed while PLC is not connected (Offline). Now offline debugging can be performed.




- 6) Click the [Tools]-[Start ladder logic test] menu of GPPW to end the Logic Test function (LLT).


# 5 Useful functions

## 3.2 Creating emulation of I/O and special unit


This section explains creating emulation of I/O and special unit such as "turning X0 ON when Y5 and Y7 are ON."




Operations for creating the emulation as shown on the left are explained. (I/O system is set in setting No.1.)



- 1) Click the [Start]-[I/O system settings] menu of the Logic Test function (LLT).



- 2) Double click the upper text box of the setting No.1 [Condition].




- 3) Set the device name (Y), device number (2), and ON/OFF designation (ON).

4) Click here

- 4) Click the **OK** button.

**To the following page //**

**From previous page //**




5) The setting result is displayed.




**Hint!**

Setting can also be done by inputting "Y2=ON".




6) Repeat steps 2) to 5) for setting the lower text box.

7) Click the [AND] radio button.



8) Input "500" (5 sec) to the [Timer] text box.




9) Double click the [Input(Simulation Device)] text box.



**To the following page //**


## 5 Useful functions

*From previous page*



10) Set the device name (X) and the device number (5).

11) Click the  button.




12) The setting result is displayed.




**Hint!**

Setting can also be done by inputting "X5".

13) Click the  ON radio button.



14) Click the check to put a check mark to validate the setting.




15) Click the  button at the lower-left of the screen.




*To the following page*

**From previous page**



16) Input the file name to save the created emulation.  
(Input "Sample.txt" here.)

17) Click the **Save** button.




18) Click the **Yes** button.

# 5 Useful functions


## 3.3 Monitoring device status

Operations such as monitoring devices, turning ON/OFF bit devices positively, and changing word device values are described.


This section explains monitoring bit device "X" and word device "D".



- 1) Click the [Start]-[Device memory monitor] menu of the Logic Test function (LLT).



- 2) Click the [Device Memory]-[Bit Device]-[X] of the device memory monitor.




- 3) The status of the bit device "X" is displayed.

### Point


Bit devices that are turned ON is displayed in yellow.

**To the following page //**


**From previous page**



- 4) Click [Device Memory]-[Word Device]-[D] of the device memory monitor.



- 5) Status of word device "D" is displayed.




- 6) Confirm that monitoring is ON.

**Hint!**


If the monitoring is OFF, click the **F3:START/STOP** button to start monitoring.

## 5 Useful functions

### —Turning ON/OFF bit device positively—



- 1) Double click the device No. to be turned ON/OFF positively.




- 2) The designated bit device No. is turned ON and displayed in yellow.

— Changing device value of word device —




1) Double click the device number for changing device value.



2) Click the number and symbol buttons to set the device value. (Here, set the value to "5".)

3) Click the **SET** button.



4) The device value is set to "5".

**MEMO**


A large, empty rectangular area with rounded corners, intended for writing a memo. The area is defined by a thick black border and occupies most of the page below the 'MEMO' header.

# *Appendix*

## **Appendix**

**Appendix**

App. 1 Short cut key list ..... A-1  
App. 2 Circuit creation list ..... A-7



# Appendix

## Appendix

### App. 1 Short cut key list

Short cut key		Tool button	Function		
Alt + F4		—	Close		
Ctrl + F6		—	Next window		
Ctrl + N			Project	New project	
Ctrl + O				Open project	
Ctrl + S				Overwrite project	
Ctrl + P				Print	
Ctrl + Z			Edit	Undo	
Ctrl + X				Cut	
Ctrl + C				Copy	
Ctrl + V				Paste	
Ctrl + A		—		Select all	
Shift + Ins		—		Insert row	
Shift + Del		—		Delete row	
Shift + F2				Read mode	
Ctrl + Ins		—		Insert column	
Ctrl + Del		—		Delete column	
F2				Write mode	
GPPA GPPQ	F5			Circuit symbol	Open contact
MEDOC	1				Close contact
GPPA	Shift + F5				
GPPQ	F6				
MEDOC	2				

	Description
	Close the active window.
	Open the next window.
	Save project as a new file.
	Open an existing project file.
	Overwrite the project file.
	Print the project.
	Undo the previous operation.
	Move the selected data to the clipboard.
	Copy the selected data to the clipboard.
	Paste the data on the clipboard to the cursor position.
	Select all items.
	Insert a row to the cursor position.
	Delete a row at the cursor position.
	Set to read mode.
	Insert a column to the cursor position.
	Delete a column at the cursor position.
	Set to write mode.
	Write an open contact to the cursor position.
	Write a close contact to the cursor position.

# Appendix

Short cut key		Tool button	Function
GPPA	F6		Open branch
GPPQ	Shift + F5		
MEDOC	3		Close branch
GPPA GPPQ	Shift + F6		
MEDOC	4		Coil
GPPA GPPQ	F7		
MEDOC	7		Application instruction
GPPA GPPQ	F8		
MEDOC	8		Horizontal line
GPPA GPPQ	F9		
MEDOC	6		Vertical line
GPPA	F10		
GPPQ	Shift + F9		Delete horizontal line
MEDOC	5		
GPPA GPPQ	Ctrl + F9		Delete vertical line
MEDOC	9		
GPPA GPPQ	Ctrl + F10		Rising pulse
MEDOC	0		
	Shift + F7		Falling pulse
	Shift + F8		
	Alt + F7		Rising pulse open branch
	Alt + F8		Falling pulse close branch
	Alt + F5		Convert operation results to rising pulse
	Ctrl + Alt + F5		Convert operation results to falling pulse

	<b>Description</b>
	Write an open branch to the cursor position.
	Write a close branch to the cursor position.
	Write a coil (OUT) to the cursor position.
	Write an application instruction to the cursor position.
	Write a horizontal line to the cursor position.
	Write a vertical line to the cursor position.
	Delete a horizontal line at the cursor position.
	Delete a vertical line at the cursor position.
	Write a rising pulse to the cursor position.
	Write a trailing pulse to the cursor position.
	Write a rising pulse open branch to the cursor position.
	Write a trailing pulse close branch to the cursor position.
	Write a convert operation results to rising pulse to the cursor position.
	Write a convert operation results to falling pulse to the cursor position.

# Appendix

Short cut key		Tool button	Function		
Ctrl + Alt + F10			Edit	Circuit symbol	Invert operation results
GPPA GPPQ MEDOC	Alt + F10				Write horizontal rule
	F10				Delete horizontal rule
	Alt + F9		Convert		Convert
Ctrl + Alt + F4					Convert (all program being edited)
	Shift + F4	—			Convert (write during run)
	Ctrl + F5	—	Display		Display comment
	Ctrl + F7	—			Display statement
	Ctrl + F8	—			Display note
Ctrl + Alt + F5		—			Display system name
	Alt + 0				Project data list
	F3		Online	Monitor	Monitor
	Ctrl + F3	—			Monitor (all windows)
	Shift + F3				Monitor (write mode)
	F3				Monitor start
	Alt + F3				Monitor stop
Ctrl + Alt + F3		—			Monitor stop (all windows)
	Alt + 1		Debug		Device test
	Alt + 2				Skip
	Alt + 3				Partial operation
	Alt + 4				Execute step
	Alt + 6	—			Remove operation
	Alt + F1			Switch circuit/list	

	Description
	Write the reversed operation result to the cursor position.
	Write a ruled line.
	Delete a ruled line.
	Convert program.
	Convert all programs being edited in batch.
	Convert program and write to the running CPU.
	Switch ON/OFF the comment display.
	Switch ON/OFF the statement display.
	Switch ON/OFF the note display.
	Switch ON/OFF the system name display.
	Switch ON/OFF the project data list display.
	Execute circuit monitoring.
	Execute circuit monitoring for all open programs.
	Set to write mode during circuit monitoring.
	Start (restart) circuit monitoring.
	Stop circuit monitoring.
	Stop circuit monitoring for all open programs.
	Turn ON/OFF devices positively or change the present values.
	Skip the sequence program in the designated range.
	Execute part of sequence program.
	Run PLC CPU step by step.
	Carry out remote operation.
	Switch between circuit screen and list screen.

# Appendix

## App. 2 Circuit creation list

Example	List expression	Tool button	Function
	"LD X1"	 + "X1"	F5 + "X1"
	"LDI X1"	 + "X1"	Shift + F5 + "X1"
	"OR X1"	 + "X1"	F6 + "X1"
	"ORI X1"	 + "X1"	Shift + F6 + "X1"
	"OUT Y1"	 + "Y1"	F7 + "Y1"
	"MOV K1 D0"	 + "MOV K1 D0"	F8 + "MOV K1 D0"
	—	 + Number of lines	F9 + Number of lines
	—	 + Number of lines	F10 + Number of lines
	—	 + Number of lines	Ctrl + F9 + Number of lines
	—	 + Number of lines	Ctrl + F10 + Number of lines
	"ANDP X1"	 + "X1"	Shift + F7 + "X1"
	"ANDF X1"	 + "X1"	Shift + F8 + "X1"
	"ORP X1"	 + "X1"	Alt + F7 + "X1"
	"ORF X1"	 + "X1"	Alt + F8 + "X1"
	"MEP"		Alt + F5
	"MEF"		Ctrl + Alt + F5
	"INV"		Ctrl + Alt + F10
	—	 + Drag	Alt + F10 + Drag
	—	 + Drag	Alt + F9 + Drag

\*1 After inputting instructions, press the **Enter** key or click the **OK** button.

\*2 This table shows operations for keys customized for GPPA.

	Menu
	[Edit]-[Ladder symbol]-[Open contact]+“X1”
	[Edit]-[Ladder symbol]-[Close contact]+“X1”
	[Edit]-[Ladder symbol]-[Open branch]+“X1”
	[Edit]-[Ladder symbol]-[Close branch]+“X1”
	[Edit]-[Ladder symbol]-[Coil]+“Y1”
	[Edit]-[Ladder symbol]-[Application instruction]+“MOV K1 DO”
	[Edit]-[Ladder symbol]-[Horizontal line]+Number of lines
	[Edit]-[Ladder symbol]-[Vertical line]+Number of lines
	[Edit]-[Ladder symbol]-[Delete horizontal line]+Number of lines
	[Edit]-[Ladder symbol]-[Delete vertical line]+Number of lines
	[Edit]-[Ladder symbol]-[Rising pulse]+“X1”
	[Edit]-[Ladder symbol]-[Falling pulse]+“X1”
	[Edit]-[Ladder symbol]-[Rising pulse open branch]+“X1”
	[Edit]-[Ladder symbol]-[Falling pulse close branch]+“X1”
	[Edit]-[Ladder symbol]-[Convert operation results to rising pulse]
	[Edit]-[Ladder symbol]-[Convert operation results to falling pulse]
	[Edit]-[Ladder symbol]-[Invert operation results]+“X1”
	[Edit]-[Draw line]+Drag
	[Edit]-[Delete line]+Drag

**<A>**

Associating programs ..... 5- 1

**<C>**

*Circuit*

Scaling of circuit ..... 2-19

Creating a circuit with  
list expressions ..... 3- 3

Creating a circuit with tool  
buttons ..... 3- 7

Creating rules (circuit) ..... 3-27

Deleting rules (circuit) ..... 3-27

Cutting a circuit block ..... 3-21

Copying a circuit block ..... 3-21

Inserting circuits by line ..... 3-25

Deleting circuits by line ..... 3-25

Circuit creation list ..... A-7

Changing function key allocation ..... 5- 5

*Cutting*

Cutting a circuit block ..... 3-21

Cutting a comment ..... 3-51

Cutting multiple comments ..... 3-53

*Creating a ruled line*

Creating a ruled line ..... 3-27

Deleting a ruled line ..... 3-28

*Copying*

Copying a circuit block ..... 3-21

Copying a comment ..... 3-55

*Creating*

Creating a circuit (list expressions) ... 3- 3

Creating a circuit (tool buttons) ..... 3- 7

Creating a ruled line (circuit) ..... 3-27

Creating a comment ..... 3-41

Creating a statement ..... 3-45

Creating a note ..... 3-47

Creating a circuit with tool buttons ..... 3- 7

Converting ..... 3-11

Creating a comment with Excel ..... 5-19

Creating a comment with Word ..... 5-21

**<D>**

*Deleting*

Deleting circuits by line ..... 3-25

Deleting a ruled line (circuit) ..... 3-28

Deleting a comment ..... 3-51

*Device comment*

What is a comment? ..... 3-39

Creating a comment ..... 3-41

Creating a comment with Excel ..... 5-19

Creating a comment with Word ..... 5-21

Editing a comment ..... 3-49

Deleting and cutting a comment ..... 3-51

Deleting and cutting multiple  
comments ..... 3-53

Copying a comment ..... 3-55

Display format of edit screen ..... 2-20

**<E>**

*Ending*

Ending GPPW ..... 2-13

Edit screen ..... 2- 8

**<G>****GPPW**

- What GPPW can do ..... 1- 1
- Installation ..... 1- 5
- System configuration ..... 1- 9
- Operation flow ..... 1-11
- Screen configuration ..... 2- 7
- Starting GPPW ..... 2-11
- Ending a GPPW session ..... 2-13
- Editing multiple GPPWs  
simultaneously ..... 5-23

**<I>**

- Installation ..... 1- 5

**<L>****Logic Test function**

- Procedures for operation ..... 5-27
- Creating emulation ..... 5-29
- Monitoring device status ..... 5-33

**<M>**

- Mouse operations to enlarge window ..... 2- 3

**Mouse operation**

- Basic operation ..... 2- 1
- Enlarging window ..... 2- 3
- Scroll bar operation ..... 2- 3
- Menu operation ..... 2- 4
- Project list operation ..... 2- 4
- Dialog box operation ..... 2- 5

- Menu bar ..... 2- 8

**<N>****Note**

- What is a note? ..... 3-40

- Creating a note ..... 3-45

- Searching a note ..... 3-57

- Editing a note ..... 3-59

**<O>****Online change**

- Writing data during run of  
the PLC CPU ..... 4-12
- Changing data during monitoring ..... 4-14

**Online operations**

- Writing and reading ..... 4- 1
- Monitoring circuit status ..... 4- 4
- Monitoring designated device ..... 4- 6
- Turning ON/OFF contact positively ..... 4- 8
- Executing program step by step ..... 4-10

- Operating the scroll bar with mouse ..... 2- 3

- Operation flow-chart ..... 1-11

- Operating dialog box with mouse ..... 2- 5

**<P>****Printing**

- Printing circuit ..... 3-61
- Printing contacts or coils in use ..... 3-63
- Printing device in use ..... 3-65
- Printing listed device  
comment in use ..... 3-67

**Project**

- What is a project? ..... 2- 9
- Designation of a project ..... 2-15
- Setting of a project ..... 2-17
- Creating a project ..... 3- 1
- Saving a project ..... 3-15
- Reading a project ..... 3-17

Opening the designated project  
at start-up ..... 5- 7  
Editing multiple projects  
simultaneously ..... 5-23  
Mouse operation of project list ..... 2- 4  
Project list ..... 2- 8

**<R>**

Replacing

Replacing with designated device ..... 3-33  
Replacing A contact with B contact  
and vice versa ..... 3-37

Reading (project) ..... 3-17

Reading a GPPA file on GPPW ..... 5- 9

**<S>**

Screen configuration

Title bar ..... 2- 8  
Menu bar ..... 2- 8  
Project data list ..... 2- 8  
Edit screen ..... 2- 8

Starting

Starting GPPW ..... 2-11  
Opening the designated  
project during start-up ..... 5- 7

Searching a circuit

Searching with designated device ..... 3-29  
Searching with step No. .... 3-31  
Searching with statement ..... 3-57  
Searching with note ..... 3-57

System configuration ..... 1- 9

Short cut key list ..... A-1

Status bar ..... 2- 8

Statement

What is statement? ..... 3-40  
Creating a statement ..... 3-45  
Searching a statement ..... 3-57  
Editing a statement ..... 3-59

**<T>**

To start-up GPPW with  
the designated project ..... 5- 7

Title bar ..... 2- 8

**<W>**

What GPPW can do ..... 1- 1

**GPP Function software for Windows  
SW2D5C-GPPW-E SW2D5C-LLT-E  
SW2D5F-GPPW-E SW2D5F-LLT-E  
Starting GPPW**

MODEL	SW2D5-GPPW-HOW-E
MODEL CODE	13J939
SH(NA)-4006-B(9810)MEE	



HEAD OFFICE : MITSUBISHI DENKI BLDG MARUNOUCHI TOKYO 100-0005 TELEX : J24532 CABLE MELCO TOKYO  
NAGOYA WORKS : 1-14 , YADA-MINAMI 5 , HIGASHI-KU, NAGOYA , JAPAN

When exported from Japan, this manual does not require application to the Ministry of International Trade and Industry for service transaction permission.

Specifications subject to change without notice.